D imprivata[®]

Product Documentation

Virtual Appliance Guide

Imprivata Enterprise Access Management

© 2025 Imprivata, Inc. All Rights Reserved.

Contacting Imprivata

20 CityPoint, 480 Totten Pond Road, 6th Floor Waltham, MA 02451 USA Phone: 781-674-2700 Toll-Free: 1-877-OneSign Fax: 1 781 674 2760 Support: 1 800 935 5958 (North America) Support: 001 408-987-6072 (Outside North America) https://www.imprivata.com support@imprivata.com

Copyright and Legal Information

© 2025 Imprivata, Inc. All Rights Reserved.

This product is distributed under licenses restricting its use, copying, distribution and decompilation. Imprivata's products may be covered in whole or in part by one or more U.S. pending or issued patents listed at http://www.imprivata.com/patents.

Trademark Information

OneSign, Imprivata, and the Imprivata logo are registered trademarks of Imprivata, Inc. ProveID and Imprivata OneSign APG are trademarks of Imprivata, Inc. in the United States and in other countries.

Legal Notices

Under international copyright laws, neither the documentation nor software may be copied, photocopied, reproduced, translated, or reduced to any electronic medium or machine-readable form, in whole or in part without the prior written consent of Imprivata, Inc., except as described in the license agreement.

The names of companies, products, people, and/or data mentioned herein are fictitious and are in no way intended to represent any real individual, company, product, or event, unless otherwise noted. DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Document revision

Table of Contents

About this Guide	
Appliance System Requirements and Guidance	
System Requirements	
Considerations for Storage Level RAID Protection	
Number of Appliances to Deploy	
G4 Appliances	
Network Services Configuration	
IP Address and Default Gateway Configuration	8
DNS Server Configuration	8
NTP Server Configuration	9
Deploy a VMware Appliance	10
Deploying the Imprivata OVF template	10
Disabling the vApp Options	10
Adding the Appliance to the Network	
Accessing the Virtual Appliance Functions	
Troubleshooting	
Verify the RAR File Download	
Issues Deploying OVF File to VMware	
Deploy a Microsoft Hyper–V Appliance	
Deploying the Imprivata VHD Image	
Adding the Appliance to the Network	
Accessing the Virtual Appliance Functions	
Deploy a Nutanix Appliance	
Creating the Appliance Image	
Creating the Virtual Machine	
Adding the Appliance to the Network	
Power on the Virtual Machine	
Configure the Network Settings	
Accessing the Virtual Appliance Functions	
Troubleshooting	
Verify the RAR File Download	
Issues Deploying OVF File to Nutanix	
Deploy to a VMware ESX Thin-Provisioned Environment	
Managing Thin-Provisioned Virtual Appliances	
Replacing Existing Imprivata Virtual Appliances with Thin-Provisioned Imprivata Virtual Appliances	
Deploying a Thin-Provisioned Imprivata Virtual Appliance	
Deploy G4 Appliances on Azure	
Assumptions	
Before You Begin	
Multiple Azure Hub-and-Spoke Topologies Supported	
G4 Appliance Basic Specifications on Azure	
Number of G4 Appliances to Deploy on Azure	
Network Services Configuration	
Deploying the Appliances	
Gathering the Azure and G4 Appliance Data Needed for Deployment	
Considering Additional Issues	
Deploying the G4 Appliances from the Azure Marketplace	
Appliance Initialization and Setup	
Accessing the Appliance Functions	34

About this Guide



NOTE:

Beginning with 24.3, Imprivata OneSign and Imprivata Confirm ID have been renamed to Imprivata Enterprise Access Management.

Some interfaces in the Imprivata Admin Console, Imprivata Appliance Console, and documentation may retain the older Imprivata OneSign and Imprivata Confirm ID product names.

You can host and manage Imprivata virtual appliances using VMware and Microsoft Hyper-V virtualization software. Imprivata virtual appliances hosted on these platforms are formatted using the industry-standard Open Virtualization Format (OVF).

You can also host and manage Imprivata virtual appliances on Nutanix and Microsoft Azure.

This guide is applicable to:

- All maintained versions of Imprivata Enterprise Access Management (formerly Imprivata OneSign and Imprivata Confirm ID).
- G4 (fourth generation) virtual appliances.

Appliance System Requirements and Guidance

Review the following before you begin.

NOTE:

i

To deploy an Imprivata G4 (fourth generation) appliance on Microsoft Azure, skip this topic and instead see Deploy G4 Appliances on Azure for appliance guidance.

System Requirements

System requirements vary by the appliance generation. For appliance system requirements, see the *Supported Components* in the <u>Imprivata Environment Reference</u>.

The release introduction history of supported appliances is:

- Imprivata OneSign 7.11 and later releases require G4 (fourth generation) appliances.
- Imprivata OneSign 7.10 introduced the General Availability (GA) release of the G4 appliance to all customers, including for G3 or G2 enterprise migrations to G4.

Imprivata OneSign 7.10, 7.9, and 7.8 supported either G3 or G4 appliances, but not both G3 and G4 appliances on the same enterprise.

- Imprivata OneSign 7.8 introduced the Controlled Availability (CA) release of the G4 appliance to select customers or on request.
- All maintained releases of Imprivata OneSign, up to 7.10, required G3 appliances.

IMPORTANT:

G3 appliances reached the end of maintenance as of December 31, 2023. For more information, see the Imprivata Product Lifecycle Matrix.

Unsupported

(i

The following virtual appliance configurations are not supported:

- The cloning of appliance virtual machines is not supported.
- Infrastructure-level snapshots of appliance virtual machines are not supported.

Considerations for Storage Level RAID Protection

While most customers will want to use RAID 5, Imprivata recommends RAID 1+0 or RAID 10 for any appliances that are experiencing a challenge with throughput, especially G4 database appliances.

Number of Appliances to Deploy



NOTE:

For specific questions about enterprise configuration or additional guidance, contact Imprivata services or support.

G4 Appliances

The number of appliances appropriate for a G4 enterprise depends on many factors, including user counts, authentication methods, and other issues.

First, consider the two G4 appliance types and the limits on their numbers per enterprise:

- Database appliances host the databases, perform database replication, service endpoint agent requests, and contain all audit data.
 - Enforced maximum of two database appliances per enterprise.
 - The first two appliances configured are always database appliances.
- Service appliances exclusively service endpoint agent requests.
 - Recommended maximum of four service appliances per enterprise.
- Recommended maximum of six total appliances per enterprise. Adding more appliances beyond six typically does not yield performance improvements.
- No audit appliances.

For G4 appliances, Imprivata recommends three standard deployment options: two-, four-, and sixappliance enterprises. The two-appliance enterprise offers three different CPU and RAM configuration options for scale.

Recommended Options	2 A	ppliance Enterp	rise	4 Appliance Enterprise	6 Appliance Enterprise
Database appliances	2	2	2	2	2
CPUs per appliance	4	8	8	8	8
RAM (GB) per appliance	8	16	32	16	16
Service appliances				2	4
CPUs per appliance				2	2
RAM (GB) per appliance				8	8
Total appliance CPUs in enterprise	8	16	16	20	24
Total appliance RAM in enterprise	16	32	64	48	64

Recommended	2 Appliance Enterprise		4 Appliance	6 Appliance	
Options			Enterprise	Enterprise	
Number of user sessions supported (in optimal conditions)	22,000 to 28,000	28,000 to 36,500	36,500 to 47,500	47,500 to 62,000	62,000 to 80,000+

NOTE:

Regarding the last row of the table above: If many or most users use Virtual Desktop Infrastructure (VDI) applications and/or desktops, then the number of user sessions can be double or triple the number of online users for the enterprise.



(i

(i)

IMPORTANT:

If you change the amount of RAM per appliance, it increases the storage required in your hypervisor environment for the virtual memory swap file for powering on the virtual appliance. Ensure that you have allocated enough storage to accommodate the change. Otherwise, powering on the virtual appliance will fail.

IMPORTANT:

G4 appliances ship with *four* CPUs by default. When deploying new G4 *service* appliances, manually remove two CPUs. These defaults and requirements do *not* apply to G4 appliances on Azure. For information on G4 appliances on Azure, see Deploy G4 Appliances on Azure.

• The base two-appliance G4 enterprise, having 4 CPUs and 8 GB RAM per appliance, totaling 8 CPUs and 16 GB RAM for the enterprise, can be equated to a base two-appliance G3 enterprise that can accommodate 22,000 to 28,000 user sessions.

Each additional column or step in the G4 table above yields approximately a 30% improvement in throughput.

- Odd numbers of appliances are recommended only when migrating from a G3 or G2 enterprise to a G4 enterprise, when the original enterprise has an odd number of appliances.
 - Migrations require the same number of G4 appliances in your new G4 enterprise as you have in your existing G3 or G2 enterprise, to support the enterprise export from G3 or G2 and import into G4.
 - For a migration with an odd number of appliances, after you transition your G4 enterprise to production, Imprivata recommends that you transition to a standard deployment configuration.
- Selecting an optimal enterprise configuration depends on knowing your total number of users and endpoints in your environment, usage patterns to identify peak activity periods, and disaster recovery needs that may stretch the topologies and halve the resources for active/active type setups.

There are many factors that affect performance including authentication types, multi-factor authentication methods, EPCS (electronic prescription of controlled substances) workflows, underlying hardware options for hosting the virtual machines that host the appliances, underlying network topology, and more.

Newer high performing systems may yield better throughputs, and conversely older systems may yield poorer performance.

• For customers with active G3 enterprises larger than two appliances, the rule of thumb is to first count the total number of CPUs in your current deployment. Then in the G4 table above, in row **Total appliance CPUs in enterprise**, find a G4 configuration with a matching CPU count.

Network Services Configuration

The Imprivata appliance supports the initial assignment of the following:

- IP address, subnet mask, and default gateway.
- DNS servers.
- NTP servers from the <u>NTP Pool Project</u>.

IP Address and Default Gateway Configuration

As part of the initialization process, an IP address, subnet, and default gateway are initially assigned.

This is achieved using either DHCP, if enabled in your environment, or later using the Imprivata Appliance Console when adding the appliance to a network. If required, you can change the settings using one of the following:

- The Imprivata Appliance Console before running the Imprivata appliance configuration (setup) wizard.
- The Imprivata Appliance Console (https://<appliance IP address>:81/) after completing the appliance configuration (setup) wizard.



NOTE: If DHCP is used to assign these values, be sure to take the necessary steps to prevent duplicate IP address conflicts on the DHCP network. The Imprivata appliance requires a static IP address.

DNS Server Configuration

As part of the initialization process, up to three DNS servers are initially assigned.

- This is achieved using either DHCP, if enabled in your environment, or using the Imprivata Appliance Console.
- If required, the appliance configuration (setup) wizard lets you change these settings as part of the initial setup of the network services. Additionally, after the appliance has been added to the enterprise, you can use the Imprivata Appliance Console (Network > Name Resolution) to update them.

NTP Server Configuration

As part of the initialization process, the following servers from the North American pool are configured by default:

- 0.north-america.pool.ntp.org
- 1.north-america.pool.ntp.org
- 2.north-america.pool.ntp.org

If required, the appliance configuration wizard lets you change these settings as part of the initial setup of the network services. Additionally, after the appliance has been added to the enterprise, you can use the Imprivata Appliance Console (**Network** > **NTP**) to update them.



NOTE: If you choose to change the defaults, configure at least two external internet-based NTP servers for redundancy. Internal NTP servers are not recommended.

Using an internal NTP server or a Windows Server as an NTP source is not recommended. Windows does not correct any offset that may occur. Windows will keep adding to the offset and eventually an error will occur.

Deploy a VMware Appliance

The following sections detail how to install a virtual appliance to VMware and add it to the network.

Deploying the Imprivata OVF template

To deploy the appliance:

1. From your fulfillment letter, download and extract the Imprivata Virtual Appliance RAR file.



NOTE: If deploying to VMware ESXi 6.7, deploy one appliance at a time. Deploying multiple appliance in parallel can result in the process timing out.

- 2. In the vSphere Client, click **File > Deploy OVF template**.
- 3. Follow the **OVF Deploy Template** wizard to complete the deployment. Consider the following:
 - Be sure to select the .mf, .ovf, and .vmdk files.



NOTE: ESXi 6.7 only — Select only the **.ovf** and **.vmdk** files.

- When prompted to customize **Networking Properties**, either select DHCP if enabled in your environment, or leave all values blank and then later network the appliance using the appliance configuration (setup) wizard.
- When prompted to review the settings, be sure that **Power on after deployment** is not selected before you finish the deployment.



NOTE: For more information on deploying an OVF template, see the VMware vSphere documentation.

Disabling the vApp Options

To disable the vApp options:

- 1. In the vSphere Client, right-click the virtual appliance, click **Edit Settings**, and open the **Options** tab.
- 2. Click vApp options, and select Disable.

A message appears that prompts you to confirm the action.

3. Click Yes, and then click OK.

Adding the Appliance to the Network

To add the appliance to the network:

- 1. Power on the appliance, and open the console to start the appliance initialization scripts.
 - The initialization scripts run in the background and do not display progress. The time to complete is approximately 15 minutes.
 - The Imprivata Appliance Console displays the IP address, subnet mask, and gateway that is initially assigned to the appliance. For more information, see Appliance System Requirements and Guidance.
- 2. (Optional, or if DHCP is unavailable on your network) If required, you can add or change the network configuration manually:
 - a. At the login prompt type menu, and then press Enter.
 - b. Type **1**, and then press **Enter** to assign or reassign the values.



NOTE: If you receive a database error message when trying to log in, the appliance has not finished initializing.

- 3. Exit the Imprivata Appliance Console.
- 4. In a web browser, enter https://<*appliance_IP_address*>:81 to complete the setup using the appliance configuration (setup) wizard.

Accessing the Virtual Appliance Functions

You access the virtual appliance function menu from the Imprivata virtual appliance menu. Not all menu options are available until you complete the Imprivata Configuration Wizard.

To access the Imprivata virtual appliance menu:

- 1. Open the virtual machine console.
- 2. Select Login and press Enter.
- 3. At the login prompt, enter **menu** and press **Enter**. If prompted, enter the menu password and press **Enter**. The Imprivata virtual appliance functions menu opens.

The menu options are:

- **Configure Network** Lets you change the default gateway for the appliance. It is for installation only. Change this setting from the Network tab under the Network page of the Imprivata Appliance Console.
- Reset SSL Clears all SSL information, including the optional SSL 2.0 setting.
- **Reset Administrator password for Imprivata Appliance Console** Resets the Administrator password to *admin*. You cannot reset the Super Administrator password.
- Modify Password for this menu Lets you set or clear the password for this menu.

- **Restage** Resets the appliance to factory settings. Contact Imprivata Customer Support for assistance with restaging an appliance.
- Restart Restarts the appliance. It is best to restart the appliance by using the Imprivata Appliance Console System page > Operations tab > Reboot/shutdown options > Reboot this appliance, unless the Imprivata Appliance Console is unreachable.
- **Shutdown** Shuts down the appliance. The Virtual Machine is still deployed in the VMware host.
- Quit

Troubleshooting

Verify the RAR File Download

Verify that the files were not corrupted during download.

- 1. In the Imprivata Virtual Appliance RAR file, there should be three files:
 - .mf a manifest files, containing checksums for the OVF and VMDK files.
 - .ovf the virtual machine template file, containing a description of the virtual machine.
 - .vmdk the virtual machine hard disk file.
- 2. Open the .mf file in a text editor. It is formatted similar to the following example:

SHA1(imprivata6.2.ovf)= a956be53480a2d6f4ca43a9c6ef46fba2e326150
SHA1(system-disk1.vmdk)= a2bedcb3bfb14e7bbbf5ad481d58104aa1ec79ba

3. Run a hash of each of these two files to verify the resulting checksums against the contents of the manifest file.

Use the following PowerShell command to get the file hash and convert it to lower case for easy comparison:

\$(Get-FileHash .\imprivata6.2.ovf -Algorithm SHA1 | Select -ExpandProperty
Hash).ToLower()

- 4. Compare the output of the PowerShell command with the checksum in the manifest file.
 - If the checksums match, it confirms that the download is good and that the extracted files are good.
 - If the checksums do not match, it indicates that the files may be corrupted and may indicate a problem with either the extraction or download process.

Recommended Steps

- 1. Do not delete the existing RAR archive; it may still be usable.
- 2. Download the archive again, using an alternate browser from the original download method. While the download is in process, you can recheck the original file:

- a. Use a different extraction utility to extract the original RAR archive. The choice of extraction utility may affect the outcome when extracting large archives.
- b. Run the checksum process on the newly extracted files to determine whether the files are good.
 - If the checksums match, cancel the new download.
 - If the checksums do not match, continue the new download and repeat the verification process.

Issues Deploying OVF File to VMware

If you experience problems deploying the OVF file, consider the following:

• When deploying, select only the OVF and VMDK files, not the MN (manifest) file.

The hypervisor may attempt to run a checksum on the manifest file, which does not contain a checksum for itself.

• Use the vSphere Web Client on Google Chrome, not Internet Explorer, to run the deployment. Internet Explorer has a maximum file size limit of 4GB, which may truncate the VMDK during the upload, causing the error:

```
The checksum(s) from the provided manifest file do not match the content of the file(s).
```

• If you still experience problems, deploy the files using the vSphere command line tool instead of the Web Client.

Example

```
ovftool.exe -ds=VMFS005_3PAR109 --net:"Network 1"="Network A VLAN 432"
-n=WSLXIMP1901 "D:\Temp\S3x64\Imprivata5.5hf1demo_0VF10.ovf"
vi://adminrb@100.64.0.25/
```

Syntax

```
ovftool --net: "source_network_name"="destination_network_name"
-ds="destination_datastore" -n="destination_virtual_machine_name"
"vi://domain\username@source_vcenter_fqdn/source_datacenter_name/
virtual_machine_name/virtual_machine_folder/virtual_machine"
"vi://domain\username@destination_vcenter_fqdn/host/cluster_name"
```

Deploy a Microsoft Hyper–V Appliance

The following sections detail how to install a virtual appliance to Microsoft Hyper–V and add it to the network.

Deploying the Imprivata VHD Image

To deploy the appliance:

- 1. From your fulfillment letter, download and extract the Imprivata Virtual Appliance RAR file.
- 2. In the Hyper-V Manager, click **Action** > **Import Virtual Machine**.
- 3. Browse to imprivataversion. Version specifies the version of the appliance.
- 4. Click Next.
- 5. Choose the type of import to perform:
 - **Register** You have an environment where you have already put all of the virtual machine files exactly where you want them, and you only need Hyper-V to begin using the virtual machine as is.
 - Restore Your virtual machine files are stored on a file share, or removable drive. For example

 you want Hyper-V to move the files to the appropriate location for you, and then register the virtual machine.
 - Copy You have a set of virtual machine files that you want to import multiple times. For example — using them as a template for new virtual machines. This selection copies the files to an appropriate location, gives the virtual machine a new unique ID, and then registers the virtual machine.
- 6. Click **Next**, and follow the wizard to complete the deployment.
- 7. In the Hyper–V Manager, right–click the appliance, and click **Settings**.
- 8. Select Network Adapter, connect to a virtual switch, and click OK.

Adding the Appliance to the Network

To add the appliance to the network:

- 1. Power on the appliance, and open the console to start the appliance initialization scripts.
 - The initialization scripts run in the background and do not display progress. The time to complete is approximately 15 minutes.
 - The Imprivata Appliance Console displays the IP address, subnet mask, and gateway that is initially assigned to the appliance. For more information, see Appliance System Requirements and Guidance.

- 2. (Optional, or if DHCP is unavailable on your network) If required, you can add or change the network configuration manually:
 - a. At the login prompt type menu, and then press Enter.
 - b. Type **1**, and then press **Enter** to assign or reassign the values.



NOTE: If you receive a database error message when trying to log in, the appliance has not finished initializing.

- 3. Exit the Imprivata Appliance Console.
- 4. In a web browser, enter https://<appliance_IP_address>:81 to complete the setup using the appliance configuration (setup) wizard.

Accessing the Virtual Appliance Functions

You access the virtual appliance function menu from the Imprivata virtual appliance menu. Not all menu options are available until you complete the Imprivata Configuration Wizard.

To access the Imprivata virtual appliance menu:

- 1. Open the virtual machine console.
- 2. Select Login and press Enter.
- 3. At the login prompt, enter **menu** and press **Enter**. If prompted, enter the menu password and press **Enter**. The Imprivata virtual appliance functions menu opens.

The menu options are:

- **Configure Network** Lets you change the default gateway for the appliance. It is for installation only. Change this setting from the Network tab under the Network page of the Imprivata Appliance Console.
- **Reset SSL** Clears all SSL information, including the optional SSL 2.0 setting.
- **Reset Administrator password for Imprivata Appliance Console** Resets the Administrator password to *admin*. You cannot reset the Super Administrator password.
- Modify Password for this menu Lets you set or clear the password for this menu.
- **Restage** Resets the appliance to factory settings. Contact Imprivata Customer Support for assistance with restaging an appliance.
- Restart Restarts the appliance. It is best to restart the appliance by using the Imprivata Appliance Console System page > Operations tab > Reboot/shutdown options > Reboot this appliance, unless the Imprivata Appliance Console is unreachable.
- **Shutdown** Shuts down the appliance. The Virtual Machine is still deployed in the VMware host.
- Quit

Deploy a Nutanix Appliance


The following sections detail how to install a virtual appliance to Nutanix and add it to the network.

Creating the Appliance Image

You upload the Imprivata VMDK file (system-disk1) to create the appliance image.

To create the image:

- 1. From your fulfillment letter, download and extract the Imprivata Virtual Appliance RAR file.
- 2. In the Prism UI, select **Settings** from the main menu.



- 3. On the Settings page, click Image Configuration, and then click Upload Image.
- 4. Enter a name for the image.
- 5. From the Image Type list, select Disk.
- 6. Select a storage container, specify the image source location, and then click **Save**.

Creating the Virtual Machine

To deploy the appliance:

1. In Prism UI, select **VM** from the main menu, and then click **Create VM**.

× –		VМ	-	🐥 2 •	0 3 ~
Overview	v → Table			+	Create VM

- 2. On the **Create VM** dialog:
 - a. Enter a name and select a timezone.
 - b. Under **Compute Details**, allocate the minimum required RAM and CPU, and then click **Add New Disk.**

See "*Imprivata OneSign Supported Components*" in the <u>Imprivata Environment Reference</u> for the minimum requirements.

3. On the Add Disk dialog:

- a. From the Operation list, select Clone from Image Service .
- b. From the **Image** list, select the appliance image that was created using the Imprivata VMDK file, and click **Add**.
- 4. On the **Create VM** dialog:
 - a. Under **Disks**, select **Disk** as the boot device.
 - b. Under Network Adapters (NIC), click Add New NIC.
- 5. On the Create NIC dialog:
 - a. From the VLAN list, select the target virtual LAN.
 - b. Deploy the NIC in a **Connected** state, and then click **Add**.
- 6. On the Create VM dialog, click **Save**.

Adding the Appliance to the Network

The following procedures detail how to add the appliance to the network.

Power on the Virtual Machine

1. In the Prism UI, select VM from the main menu, and then click Table.

\mathbf{X}	/M ~	. 🧇 .	🐥 2 •	0 3 *
Overview · Table			+	Create VM

- 2. Locate the virtual machine, click the name, and then click **Power on**.
- 3. Click Launch Console.

(i)

NOTE: The initialization scripts run and display progress. The time to complete is approximately 15 minutes. If you receive a database error messaging when trying to log in, the appliance has not finished initializing.

Configure the Network Settings

To add the appliance to the network:

- 1. Power on the appliance, and open the console to start the appliance initialization scripts.
 - The initialization scripts run in the background and do not display progress. The time to complete is approximately 15 minutes.
 - The Imprivata Appliance Console displays the IP address, subnet mask, and gateway that is initially assigned to the appliance. For more information, see Appliance System Requirements and Guidance.

- 2. (Optional, or if DHCP is unavailable on your network) If required, you can add or change the network configuration manually:
 - a. At the login prompt type menu, and then press Enter.
 - b. Type **1**, and then press **Enter** to assign or reassign the values.



NOTE: If you receive a database error message when trying to log in, the appliance has not finished initializing.

- 3. Exit the Imprivata Appliance Console.
- 4. In a web browser, enter https://<appliance_IP_address>:81 to complete the setup using the appliance configuration (setup) wizard.

Accessing the Virtual Appliance Functions

You access the virtual appliance function menu from the Imprivata virtual appliance menu. Not all menu options are available until you complete the Imprivata Configuration Wizard.

To access the Imprivata virtual appliance menu:

- 1. Open the virtual machine console.
- 2. Select Login and press Enter.
- 3. At the login prompt, enter **menu** and press **Enter**. If prompted, enter the menu password and press **Enter**. The Imprivata virtual appliance functions menu opens.

The menu options are:

- **Configure Network** Lets you change the default gateway for the appliance. It is for installation only. Change this setting from the Network tab under the Network page of the Imprivata Appliance Console.
- **Reset SSL** Clears all SSL information, including the optional SSL 2.0 setting.
- **Reset Administrator password for Imprivata Appliance Console** Resets the Administrator password to *admin*. You cannot reset the Super Administrator password.
- Modify Password for this menu Lets you set or clear the password for this menu.
- **Restage** Resets the appliance to factory settings. Contact Imprivata Customer Support for assistance with restaging an appliance.
- Restart Restarts the appliance. It is best to restart the appliance by using the Imprivata Appliance Console System page > Operations tab > Reboot/shutdown options > Reboot this appliance, unless the Imprivata Appliance Console is unreachable.
- **Shutdown** Shuts down the appliance. The Virtual Machine is still deployed in the VMware host.
- Quit

Troubleshooting

Verify the RAR File Download

Verify that the files were not corrupted during download.

- 1. In the Imprivata Virtual Appliance RAR file, there should be three files:
 - .mf a manifest files, containing checksums for the OVF and VMDK files.
 - .ovf the virtual machine template file, containing a description of the virtual machine.
 - .vmdk the virtual machine hard disk file.
- 2. Open the .mf file in a text editor. It is formatted similar to the following example:

```
SHA1(imprivata6.2.ovf)= a956be53480a2d6f4ca43a9c6ef46fba2e326150
SHA1(system-disk1.vmdk)= a2bedcb3bfb14e7bbbf5ad481d58104aa1ec79ba
```

3. Run a hash of each of these two files to verify the resulting checksums against the contents of the manifest file.

Use the following PowerShell command to get the file hash and convert it to lower case for easy comparison:

```
$(Get-FileHash .\imprivata6.2.ovf -Algorithm SHA1 | Select -ExpandProperty
Hash).ToLower()
```

- 4. Compare the output of the PowerShell command with the checksum in the manifest file.
 - If the checksums match, it confirms that the download is good and that the extracted files are good.
 - If the checksums do not match, it indicates that the files may be corrupted and may indicate a problem with either the extraction or download process.

Recommended Steps

- 1. Do not delete the existing RAR archive; it may still be usable.
- Download the archive again, using an alternate browser from the original download method.
 While the download is in process, you can recheck the original file:
 - a. Use a different extraction utility to extract the original RAR archive. The choice of extraction utility may affect the outcome when extracting large archives.
 - b. Run the checksum process on the newly extracted files to determine whether the files are good.
 - If the checksums match, cancel the new download.
 - If the checksums do not match, continue the new download and repeat the verification process.

Issues Deploying OVF File to Nutanix

If you experience problems deploying the OVF file, consider the following:

• When deploying, select only the OVF and VMDK files, not the MN (manifest) file. The hypervisor may attempt to run a checksum on the manifest file, which does not contain a checksum for itself.

Deploy to a VMware ESX Thin-Provisioned Environment

Imprivata virtual appliances can be deployed using VMware ESX thin-provisioning. These appliances have the same performance as standard virtual appliances, as determined by the ESX infrastructure. Disk provisioning selection does not affect memory, CPU, and other Imprivata virtual appliance allocations.

NOTE:

(i)

Thin-provisioned virtual appliances never shrink in size when space is allocated by the hypervisor. This is a limitation of ESX Thin Provisioning, and is not limited to the Imprivata virtual appliance. You may see significant increases in Imprivata virtual appliance disk sizes if an appliance is unreachable for replication traffic in a problem situation. The only way to recover disk space is to replace appliances (see Replacing Existing Imprivata Virtual Appliances with Thin-Provisioned Imprivata Virtual Appliances).

Managing Thin-Provisioned Virtual Appliances

Carefully monitor the virtual appliance deployment space, for both the hypervisor (datastore) and the storage device (local disk, SAN, NFS). The initial thin-provisioned size of the virtual appliance is about 20 GB. The maximum thin-provisioned virtual appliance disk usage is 250 GB plus 8 GB of memory. The virtual appliance guest assumes it has a 250 GB disk available. If the storage device or datastore runs out of space, then the virtual appliance fails at the first event that requires more disk space. You can monitor virtual appliance disk usage in ESX, in the Imprivata Appliance Console **System** page **Operations** tab, or in the appliance logs.

CAUTION:

/!\

There is **no warning** if the hypervisor cannot allocate more disk space for the Imprivata virtual appliance. The host and Imprivata continue to operate normally until disk space runs out, and then unpredictable problems occur. Assume that, in this case, Imprivata Enterprise Access Management shuts down and does not provide service to users.

Replacing Existing Imprivata Virtual Appliances with Thin-Provisioned Imprivata Virtual Appliances

To replace existing virtual appliances with thin-provisioned virtual appliances:

- 1. Remove the existing Imprivata virtual appliance from the enterprise. Confirm that the virtual appliance is powered off.
- 2. Deploy the new thin-provisioned Imprivata virtual appliance.

- Synchronize the enterprise database from the Imprivata Appliance Console System page > Operations tab.
- 4. Add the thin-provisioned virtual appliance to the enterprise.
- 5. Delete the original virtual appliance.

Deploying a Thin-Provisioned Imprivata Virtual Appliance

To deploy a virtual appliance to a thin-provisioned ESX disk:

1. Log into VMware vSphere Client and **Create a new virtual machine** as you would for a standard VM, but for **Disk Format**, select **Thin provisioned format** instead as shown in the following image:

Ø Deploy OVF Template	
Disk Format In which format do you wa	nt to store the virtual diska?
Constant Constantiate Creating Time and Location B 19581/Constant Time And Constantiate Time And Constantiate	Information about the selected datastore: Marine marks 4 DO Copesities 331.08 Sherts atomatin which to store the withaul motives virtual disks: Sherts atomatin which to store the withaul motives virtual disks: This providenced format The storage is allocated on demand as data is written to the virtual disks. This is could be that a storage to the set of the storage of datastores mg/t could be that a storage to the set of the storage of datastores mg/t Do That provides format All storage is allocated in mediately. Estimated disk usage: 250.0 (d)
Help	< Back Next > Cancel

2. Complete the process and deploy as you would for a thick-provisioned VM.



NOTE: As with all thin-provisioned VMs, the Used Storage grows over time and never diminishes of its own accord.

As the SAN fills up, you may want to recover some of that space. See Replacing Existing Imprivata Virtual Appliances with Thin-Provisioned Imprivata Virtual Appliances

Deploy G4 Appliances on Azure

The sections below describe how to deploy Imprivata G4 (fourth generation) virtual appliances on Microsoft Azure infrastructure services through the Azure Marketplace.

The release introduction history and supported migration path history of G4 and G3 (third generation) virtual appliances and enterprises **on Azure** is:

- Imprivata OneSign 23.2 supported larger scale and higher performance deployments of G4 on Azure by adding service appliances and the new migrations described in the next bullet
- Imprivata OneSign 23.2 added support for the following enterprise migrations involving Azure:
 - ° G3 on premises to G4 on Azure
 - ° G3 on Azure to G4 on Azure
 - G4 on premises to G4 on Azure
 - Hybrid G3 to hybrid G4. A hybrid G3 enterprise has some G3 appliances on premises and some on Azure, and usually supports a Disaster Recovery configuration. A hybrid G3 enterprise can be migrated to a hybrid G4 enterprise with G4 appliances on premises and on Azure.

NOTE:

 (\mathbf{i})

For the procedure for *all* migrations to a G4 enterprise, see "Migrating to a G4 Enterprise" in the <u>Imprivata Upgrade Portal</u>. **This topic you are reading becomes part of that G4 migration procedure** when you are migrating to G4 *on Azure* or doing a hybrid G3 to G4 migration, in which case this topic occurs at section "Stage a G4 Appliance on Microsoft Azure" in the G4 migration topic.

- **Beginning with 23.2**, Imprivata adopted a new numbering scheme for Imprivata OneSignImprivata Confirm ID intended to reflect the yearly release cadence. The final release in the 7.x numbering scheme was Imprivata OneSignImprivata Confirm ID 7.12.
- OneSign 7.10 through 7.12 supported G4 enterprises on Azure <u>only</u> for new enterprises of two database appliances, although new enterprises of one database appliance can be used only for testing including Proof of Concept testing. Scaling G4 appliances on Azure beyond two appliances by adding service appliances is only supported starting with OneSign 23.2 and later.
- OneSign 7.10 supported either G3 or G4 appliances on Azure, but not both G3 and G4 appliances in the same enterprise.
- OneSign 7.4 through 7.10 supported G3 appliances on Azure.

NOTE:

You establish a G4 or G3 enterprise on Azure using different **private products** in the Azure Marketplace, so be sure to select the private product for the enterprise that you want.

Both G4 and G3 products were moved in the Azure Marketplace from their previous location in "Private offers" to a new location in a "Private product" category.

Assumptions

This documentation was written applying the following assumptions:

- You are familiar with Microsoft Azure Portal and Marketplace use and terminology.
- You are familiar with Microsoft Azure IaaS (Infrastructure as a Service) services.
- You have an active Azure tenant and subscription.

NOTE:

(i)

The Imprivata appliance on Azure is available as a private product in the Azure Marketplace. Microsoft blocks access to private products for Azure subscriptions owned by Azure Cloud Solutions Providers (CSPs). Therefore, customers using a CSP subscription must get their own Azure pay as you go tenant and subscription to access and use the Imprivata appliance on Azure.

- You adopt Microsoft's networking best practices.
- You are actively engaging with Imprivata service engineers (or other appropriate Imprivata personnel or partners) to ensure deployed resources are successfully connected to existing infrastructure.

Before You Begin

Before deploying an appliance on Azure, familiarize yourself with information associated with Microsoft Azure and the Imprivata G4 appliance. Review the following documentation:

- **Microsoft Azure documentation.** Many deployment tasks in this topic are performed in the Azure Portal and Marketplace. For more information, see the Azure documentation.
- "G4 Appliance Types" in the <u>Imprivata online help</u>.
- "The Imprivata Appliance Console" in the Imprivata online help.

Multiple Azure Hub-and-Spoke Topologies Supported

You can deploy Imprivata appliances into a variety of Azure hub-and-spoke network topologies. Your Azure network topology may depend on how much of your organization's infrastructure has been

migrated from being solely on-premises to being a hybrid mix of on-premises and in-cloud. Four common Azure network topologies into which you can deploy appliances are:

- Deploy appliances into one spoke virtual network in a single region. The Microsoft Active Directory (AD) is on premises.
- Deploy appliances into one spoke virtual network in a single region. The AD is in the hub virtual network in Azure.
- Deploy appliances into more than one spoke virtual network in different regions for enhanced local service, geographic redundancy, or due to latency or volume. The AD is in the hub virtual network.
- Deploy appliances into the hub virtual network to provide shared services to multiple spoke networks. The AD is in the hub virtual network.

For more information on the hub-and-spoke architecture, see Azure documentation on <u>Hub-and-Spoke</u>.

An Active Directory Domain Controller can be located on-premises or on Azure IaaS. If a Domain Controller is located on-premises, then before deploying an appliance on Azure, consider the following information:

- An Active Directory Domain Controller should be deployed into the Shared Services subnet in the hub virtual network. This reduces network traffic from the Azure data center to your on-premises network and associated network latency and data egress costs.
- The appliances are deployed as a spoke off of this central hub network and will depend on the gateway solution for any communication to on-premises resources.
- The appliance deployment should be targeted to the same geographic region as the hub virtual network to reduce inter-regional latency and data egress costs.

G4 Appliance Basic Specifications on Azure

Imprivata G4 appliances deployed on Azure are based on the same software stack as Imprivata G4 appliances on premises. The appliance is deployed on your choice of the following two options available:

- Azure F4s_v2 virtual machine (VM) having four vCPUs, 8 GB RAM, and 300 GB of storage.
- Azure F8s_v2 virtual machine having eight vCPUs, 16 GB RAM, and 300 GB of storage.

For both options, the Azure VM manages swap space in an external resource disk.

Number of G4 Appliances to Deploy on Azure

Imprivata supports automated deployment of G4 appliances on Azure, including both database appliances and service appliances. The database appliances and service appliances can be various mixes of Azure F4s_v2 VMs and/or F8s_v2 VMs, with one important recommendation: database appliances should have the same or greater processing power and capacity than service appliances in an enterprise. You must specify appliances with enough RAM and disk resources to handle the load expected for them as database or service appliances.


For an enterprise of only two database appliances, the Azure F4s_v2s may be sufficient. For higher performance needs, you can optionally scale up to using two F8s_v2s. For a larger enterprise of four or more appliances, the database appliances must be F8s_v2s to provide sufficient performance.

The number and type of appliances appropriate for an enterprise depends on numerous factors, including user counts, authentication methods, network topology, site configuration, and failover requirements. The table below shows baseline combinations of database appliances and service appliances in an Azure G4 enterprise for best performance and cost, assuming all appliances in the enterprise are active servicing endpoint requests. Alternatively, you can deploy enterprises with an odd number of appliances, but performance will vary. Larger enterprises on Azure are supported, but may yield only marginal performance improvements.

Recommended Options	2 Appliance Enterprise	2 Appliance Enterprise	4 Appliance Enterprise	6 Appliance Enterprise	6 Appliance Enterprise
Database Appliance Azure VM Type	F4s_v2 (4 VCPUs, 8 GB)	F8s_v2 (8 VCPUs, 16 GB)	F8s_v2 (8 VCPUs, 16 GB)	F8s_v2 (8 VCPUs, 16 GB)	F8s_v2 (8 VCPUs, 16 GB)
Number	2	2	2	2	2
Service Appliance Azure VM Type	None	None	F4s_v2 (4 VCPUs, 8 GB	F4s_v2 (4 VCPUs, 8 GB	F8s_v2 (8 VCPUs, 16 GB)
Number	0	0	2	4	4
Max Performance in Authentications per Minute	7,250	11,200	13,000	14,700	16,000

Estimate the maximum number of user authentications per minute needed for your enterprise at peak usage. You can then use the last row in the table above to determine the baseline enterprise that best matches your organization's needs.

To estimate the maximum number of user authentications per minute needed for your enterprise at peak usage, use the sample information in the graphic below as a general guide. Peak usage typically occurs at or near the start of a major work shift. Your Imprivata sales engineer or support person can help you with this estimation.



IMPORTANT:

(i)

Imprivata's G4 private product in the Azure Marketplace allows you to deploy up to 10 G4 appliances on 10 virtual machines (one appliance per VM) in one Azure resource group. This allows you to deploy some G4 appliances for a production enterprise, some for a staging enterprise, and some for a testing enterprise, <u>all in the same Azure resource group</u>. If you add more G4 appliances at a later time, you must add them to a different Azure resource group, and you cannot move them into the first Azure resource group. Therefore, if possible, deploy extra appliances, and if you don't need them, remove them later.

So, you should plan how many enterprises you will create, how many database and service appliances you will create in each enterprise, and which appliances will be Azure F4s_v2s or F8s_v2s. You can deploy up to 10 G4 appliances in one deployment process, including specifying F4s_v2 or F8s_v2 per appliance, and then during the wizarded configuration process for each appliance, you assign that appliance to an enterprise. The first two appliances assigned to an enterprise are always database appliances, and any more appliances assigned to that enterprise are always service appliances. Therefore, the order in which you assign appliances to an enterprise determines their type.

Also consider Imprivata G4 site recommendations, including "active/active" setups and using no more than two sites per G4 enterprise, as described in "Imprivata Sites for G4 Enterprises" in the Imprivata online help.

NOTE:

For specific questions about enterprise configuration or additional guidance, contact Imprivata Services or Support.

Network Services Configuration

When you deploy an appliance to Microsoft Azure, the Azure DHCP service assigns a networking configuration to the appliance.



(i

CAUTION:

Do **not** change the networking configuration for the appliance (except as specified in the Note below if it applies). If you change network configuration values for the appliance, it may affect your ability to contact and control the virtual machine upon which the appliance runs.

Azure DHCP sets the following networking configuration values for the appliance that you should **not** change:

- Host name
- Domain name
- IP address
- Subnet mask
- Default gateway
- DNS servers
- NTP servers

(i)

NOTE:

If your Azure subscription uses a "Custom DNS," meaning it uses your existing DNS infrastructure instead of the Azure DNS, then you must replace the domain name for the appliance after deployment and initialization and during configuration with a setup wizard, as mentioned in Appliance Initialization and Setup.

Deploying the Appliances

Gather the required data, consider the additional issues, and perform the tasks described in sections below to locate the Imprivata G4 appliance solution in the Azure Marketplace and perform the deployments.

Gathering the Azure and G4 Appliance Data Needed for Deployment

Collect and record the following Azure and G4 appliance resource data to use in the steps in Deploying the G4 Appliances from the Azure Marketplace:

- Your Azure subscription ID.
- An Azure **resource group** where the Imprivata appliance resources will live. You can use an existing resource group only if it is empty, such that no Azure resources are defined in it. Otherwise, you must create a resource group during the deployment.
- The Azure **region** (effectively the Azure Data Center) to which the appliance(s) will be deployed, such as East US, Central US, North Central US, or West Coast US. Appliance region placement is important because it impacts the performance of access to the Imprivata Appliance Console. Please follow Microsoft's recommendations regarding region selection in regard to proximity to your end users and latencies.
- The **virtual network** for the appliance(s), including whether you want to use an existing virtual network or create a new one.
- The **subnet** for the appliance(s) on that virtual network, including whether you want to use an existing subnet or manage your existing subnet configuration.
- The **diagnostic storage account** for the appliance(s). You can choose an existing account (if one exists) or create a new one. If you will create a new diagnostic storage account, decide on a name for it. The name must be between 3 and 24 characters long, inclusive, and include only lower-case letters and numbers with no spaces.
- Decide how many G4 database and service appliances you will create for production, test, and staging enterprises, and in total. Also decide which appliances will be F4s_v2s and which F8s_v2s. For guidance, see Number of G4 Appliances to Deploy on Azure above. For an individual enterprise, most customers deploy two database appliances for redundancy, plus optional service appliances if needed for performance. For a Proof of Concept (POC) deployment, deploy one database appliance. (You can also add an appliance later to a virtual network and subnet in which an existing appliance resides, but the new appliance must be placed in a different Azure resource group.)
- One or more **virtual machine (VM) names**, one for each VM that will host an appliance. Each name can be at most 28 characters long. The default values are imp-vm-01, imp-vm-02, and so on, which you can change. Consider creating a naming convention for your VM names. The VM name is applied as a prefix to the other resources deployed, for example, the NIC, private IP address, Network Services Group (NSG), and so on.

NOTE:

If you are deploying G4 appliances on Azure as part of migrating an enterprise to G4 on Azure, or as part of migrating a hybrid G3 enterprise to G4, then host names for appliances change during the migration. However, the host names of your original appliances must match the VM names you specify when creating the new G4 appliances on Azure, because an appliance's host name must always match its VM name. Therefore, note the original appliances' host names, or copy those host names from your enterprise export file, so you can specify them as the VM names for the new G4 appliances on Azure. In the export file, a host name appears as the first part of the FQDN (Fully Qualified Domain Name) for an appliance.

Considering Additional Issues

Consider these additional issues before you begin deploying the appliance(s):

- Establish required predefined **resources for backups and archiving,** such as file shares and file transfer systems (FTS).
- Assess **Disaster Recovery** (DR) region requirements and related network connectivity.
- An Azure **availability set** is automatically created for an appliance during the deployment. The availability set effectively splits a hosting virtual machine across server racks for increased reliability. If you plan to deploy multiple appliances, a different availability set is created for each appliance.
- Consider deploying your appliance(s) in an Azure **availability zone** in the Azure region where you will deploy the appliances.
- You can apply a **network security group** for an appliance on the hosting virtual machine NIC or subgroup.

Deploying the G4 Appliances from the Azure Marketplace

To locate and deploy the Imprivata G4 appliances from the Azure Marketplace:

- 1. In the Azure Portal, search for and select Marketplace.
- 2. Select View Private Products.
- 3. Select the Imprivata G4 product.

NOTE:

i

If you do not see this product, either contact your Imprivata representative or enter your contact information in the **Contact Me for Product** window and submit that request so that Imprivata can contact you. Imprivata must make the private product visible to you before you can proceed.

Do <u>not</u> select the **Imprivata OneSign/Confirm ID Solution (Preview)** product. That is the G3 appliance on Azure product.

A page displays describing the product.

4. Select **Create**. The **Create** page for the Imprivata G4 product opens to the **Basics** tab.

NOTE:

Moving quickly through the screens of the Azure deployment wizard may result in a verification error. To resolve the error, return to the previous screen and wait a short time before proceeding.

- 5. Under **Project details,** specify or select values for these fields:
 - a. Subscription: Select your Azure subscription type, such as Pay-As-You-Go.
 - b. **Resource group:** Either specify an existing, empty resource group that has no Azure resources defined in it, or select **Create new** and in the pop-up, specify a new resource group.
- 6. Under Instance details:

Region: Select the Azure region for your appliances, which is often the region in which you are located.

- 7. Under Configure virtual networks:
 - a. Virtual network: Select an existing virtual network or click Create new to create a new one.
 - b. **Subnet**: Select an existing subnet or click **Manage subnet configuration** to manage your existing subnet configuration.

For instructions on creating a new virtual network on Azure or managing your existing subnet configuration on Azure, see Microsoft's Azure documentation.

NOTE:

i

If you are deploying G4 appliances on Azure as part of *any* enterprise migration to G4 on Azure (or to a hybrid G4 enterprise on Azure and on premises), then you must specify virtual network and subnet values here, because any network values that you later import from your original enterprise export file will not be used.

8. Under Storage account configuration:

Diagnostic storage account: Either select a value offered, if any, or click **Create New** and a frame appears on the right side of the interface. In that frame, specify a storage account name between 3 and 24 characters long, inclusive, and use only lower-case letters and numbers with no spaces. For the other three fields in the **Create storage** frame: **Account kind**, **Performance**, and **Replication**, use the default values.

- 9. Select Next: Virtual Machine Settings.
- 10. On the **Virtual Machine Settings** tab, specify or select values for the fields listed below. For guidance, see Number of G4 Appliances to Deploy on Azure above.

NOTE:

If you are deploying G4 appliances as part of migrating an enterprise to a new G4 enterprise on Azure, or as part of migrating a hybrid G3 enterprise to G4, then you must specify the host names of your original appliances in these fields as the virtual machine (VM) names for the new G4 appliances on Azure. This requirement is explained above in Gathering the Azure and G4 Appliance Data Needed for Deployment.

- a. **First Virtual Machine name:** Either leave the default value imp-vm-01 unchanged or optionally change it. Each VM name can have at most 28 characters.
- b. **First Virtual Machine size:** Specify whether to use a Standard_F4s_v2 Azure VM or a Standard_F8S_v2 Azure VM.
- c. **Second Virtual Machine name:** Either leave the default value imp-vm-02 unchanged or optionally change it.
- d. Second Virtual Machine size: Select an option to:
 - create an appliance using a Standard_F4s_v2 Azure VM
 - create an appliance using a Standard_F8S_v2
 - leave the default value selected to not deploy this appliance
- e. For each of the third through tenth VMs, either leave the default VM name unchanged or optionally change it.

For each VM, select from among the same three options as was offered for the **Second Virtual Machine size** field.

11. Click **Next: Review + create**. Azure reviews the configuration.

If the validation passes, review your displayed selections and your displayed name, email address, and phone number. If any of your contact information is missing, enter it. Then click **Create** to deploy the solution.

If the validation fails, view any error messages, resolve any issues, and click Create again.

The deployment starts and may take 5 to 10 minutes to complete.

As deployment progresses, the system displays status information. You can also confirm that deployment is in progress by clicking on the notification (bell) icon in the upper right corner of the Azure window. You can also select **Resource groups** in the Azure left frame and see your new Resource Group listed.

When the deployment is done, you can view the results in any of these ways:

- Click on the notification icon in the Azure window to view the Deployment Succeeded notification.
- From the **Notifications** drop-down, you can select **Go to resource group** and see your deployment with virtual machines, network interfaces (NICs), and disks, plus a network security group, a virtual network, a storage account, and an availability set.
- From that **Resource Group** display, you can select the virtual network to see your network settings and IP addresses.

- In the Resource Group left frame, you can select **Diagram** to see a diagram view of the network with a subnet, NICs, virtual machines, and a shared network security group.
- In that network diagram, you can select the network security group to see inbound and outbound ports with allow/deny settings and so on.

Appliance Initialization and Setup

After deployment, the appliance(s) power up automatically and initialization scripts run in the background and do not display progress. The time to complete is approximately 15 minutes for an appliance.

After that time, in a web browser, enter https://<*appliance_IP_address*>:81 to complete the setup of the first appliance using the appliance configuration wizard. During this configuration you specify the production, staging, or test enterprise to which to assign the appliance. Remember that the first two G4 appliances assigned to any G4 enterprise must be database appliances, and thereafter, all G4 appliances added to that same enterprise must be service appliances. Therefore, the order in which you assign appliances to an enterprise determines their type.

If your Azure subscription uses a "Custom DNS," meaning it uses your existing DNS infrastructure instead of the Azure DNS, then you must replace the domain name for the appliance during configuration with the wizard. In this case Azure DHCP supplies fake domain name

reddog.microsoft.com during deployment and you must replace it with your existing domain name. You do this using the Imprivata Appliance Console during the networking step of the configuration setup.

If you deployed two or more G4 appliances, repeat the processes in this section for each additional G4 appliance.

If your G4 appliance deployments are part of an enterprise migration to G4 on Azure, or are part of a hybrid G3 enterprise migration to G4, then after you have completed setup of all the new G4 appliances on Azure, return to topic "Migrating to a G4 Enterprise", section "Export the Current Enterprise" on the Imprivata Upgrade Portal to continue your migration procedures.

Accessing the Appliance Functions

To access the Imprivata appliance functions menu:

- 1. In the Azure Portal, on the **Virtual Machines** window, in the **Support + Troubleshooting** section, access the Serial Console.
- 2. Open the console for the virtual machine hosting the Imprivata appliance.
- 3. At the system prompt, enter **menu** and press **Enter**. The Imprivata appliance functions menu opens.

The menu options are:

- **Configure Network** Lets you change the default gateway for the appliance. Do <u>not</u> change this value for an appliance on Azure (see the Caution and Note in Network Services Configuration .)
- **Reset SSL** Clears all SSL information.
- **Reset Administrator password for Imprivata Appliance Console** Resets the Administrator password to *admin*. You cannot reset the Super Administrator password.
- Modify Password for this menu Lets you set or clear the password for this menu.
- **Restage** Resets the appliance to factory settings. Contact Imprivata Customer Support for assistance with restaging an appliance.
- Restart Restarts the appliance. It is best to restart the appliance by using the Imprivata Appliance Console System page > Operations tab > Reboot/shutdown options > Reboot this appliance, unless the Imprivata Appliance Console is unreachable.
- **Shutdown** Shuts down the appliance. The virtual machine is still deployed on the Azure host.
- Quit